Protocol



TD-P Revision 6.3

Creation Date: 5/7/2021 Revision Date: 2/16/2023

C58C1 Agrobacterium Chemically Competent Cells Transformation Protocol

Introduction

GoldBio's C58C1 Chemically Competent Agrobacterium cells allow you to obtain high transformation efficiency in applications such as gDNA or cDNA library construction. C58C1 has the chromosomal backbone of C58 but it has been cured of the Ti plasmid pTiC58. Our C58C1 strain harbors streptomycin and rifampicin resistance genes. C58C1 Competent cells are optimized for genetic transformation of plants such as Arabidopsis but can be used in many other plants. Here, we present a detailed protocol for transformation using C58C1 Agrobacterium Chemically Competent Cells.

Materials

- C58C1 Agrobacterium Chemically Competent Cells (GoldBio Catalog # CC-109)
- pCAMBIA1391z Control DNA, 10 ng/μl
- Agrobacterium Recovery Medium
- Kanamycin (GoldBio Catalog # K-120)
- Rifampicin (GoldBio Catalog #R-120)
- Yeast Extract Tryptone (YT) or LB Agar selection plates.
- Microcentrifuge tubes
- Shaker incubator

Storage and Handling

- This product may be shipped on dry ice. C58C1 *Agrobacterium* Chemical Competent Cells should be stored at -80°C, pCAMBIA1391z Control DNA, 10 ng/µl, should be stored at -20°C and recovery medium should be stored at 4°C immediately upon arrival. When stored under the recommended conditions and handled correctly, these products should be stable for at least 1 year from the date of receipt.
- Thaw C58C1 Agrobacterium Chemically Competent Cells and pCAMBIA1391z Control
 DNA on ice and mix by gently tapping the tube. After thawing, these products should be
 kept on ice before use.

Note: Transformation efficiency is tested by using the pCAMBIA1391z control DNA supplied with the kit and using the protocol given below. Transformation efficiency should be $\geq 1 \times 10^5$ cfu/µg pCAMBIA1391z DNA. Untransformed cells are tested for appropriate antibiotic sensitivity.



Gold Biotechnology/ FM-000008 C58C1 Agrobacterium Chemically Competent Cells Transformation Protocol TD-P Revision 6.3 TD-P Date: 2/16/2023

Method

Transformation protocol

Use this procedure to transform C58C1 *Agrobacterium* Chemically Competent Cells. Do not use these cells for electroporation.

Note: Handle the competent cells gently as they are highly sensitive to changes in temperature or mechanical lysis caused by pipetting.

Note: Thaw competent cells on ice and transform cells immediately following thawing. After adding DNA, mix by tapping the tube gently. Do not mix cells by pipetting or vortexing.

- 1. Place sterile microcentrifuge tubes on ice.
- 2. Remove competent cells from the -80°C freezer and thaw completely on ice (10-15 minutes).
- 3. Aliquot 1 μ l (50 ng to 500 ng) of DNA to the chilled microcentrifuge tubes on ice.

Note: It is important to use more DNA than in a typical bacterial transformation. We recommend using ~500 ng, if possible.

- 4. When the cells are thawed, add 50 μ l of cells to each DNA tube on ice and mix gently by tapping 4-5 times. For the pCAMBIA1391z control, add 5 μ l of (10 ng/ μ l) DNA to 50 μ l of cells on ice. Mix well by tapping. **Do not** pipette up and down or vortex to mix, this can harm cells and decrease transformation efficiency.
- 5. Keep tubes on ice for 5 minutes, and then transfer to a dry ice/ethanol bath or liquid nitrogen for 5 minutes.

Note that if you used a dry ice/ethanol bath you can place the frozen tubes on dry ice for <u>up to 30</u> minutes prior to the 37°C heat shock.

Note: For a dry ice/ethanol bath, we recommend adding ~200 ml EtOH to a used pipet tip container and slowing adding dry ice over the course of 10 minutes.

- 6. Incubate tubes in a 37°C water bath for 2 minutes (for dry ice/ethanol bath) or for 5 minutes (for liquid nitrogen).
- 7. Immediately add 950 μ l of Recovery Media and gently pipette up and down three times to resuspend the cells.

Web: www.goldbio.com
Email: contactgoldbio86@goldbio.com



Gold Biotechnology/FM-000008

C58C1 Agrobacterium Chemically Competent Cells Transformation Protocol

TD-P Revision 6.3 TD-P Date: 2/16/2023

- 8. Incubate at 30°C for 3 hours at 200 rpm in a shaking incubator.
- 9. Dilute the cells as appropriate, then spread 2 to 200 μ l cells onto a selective plate. For the pCAMBIA1391z control, plate 200 μ l of the diluted transformants onto a YT or LB plate containing 15 μ g/ml rifampicin and 50 μ g/ml kanamycin. Use a sterilized spreader or autoclaved plating beads to spread evenly.

Note: Dry plates for at least 25 minutes in a biohood for best results.

Note: For best results, we recommend spreading 2 μ l, 20 μ l and 200 μ l onto separate plates for each transformation. For the 2 or 20 μ l plates, add 200 μ l of recovery media to help spread. This helps to save time if transformation efficiencies are either very low or very high.

10. Incubate the plates for 2-3 days at 30°C.

Table 1. Antibiotic Disc Sensitivity for GoldBio's *Agrobacterium* Strains (using standard BD antibiotic discs)

	Antibiotic Selection									
Competent cells	100	100	30	Chlor 100 µg/ml	30	Kan 50 µg/ml	Rif 25 µg/ml	Spec 50 µg/ml	Strep 50 µg/ml	Tet 50 µg/ml
GV3101	I	R	R	PR	R	S	R	S	R	S
EHA 105	R	R/S	R	N/A	R/S	S	R	S	R	S
LBA 4404	S	S	S	N/A	S	S	R	S	R	S
AGL-1	R	R	R	N/A	R/S	S	R	S	R	S
C58C1	R	R	R	N/A	R/S	S	R	S	R	S

S = Sensitive

R = Resistant

R/S= intermediate zones using standard discs.

I= growth in inhibitory zone with standard disc. "Opaque", not clear zone of inhibition.

Web: www.goldbio.com
Email: contactgoldbio86@goldbio.com



Gold Biotechnology/ FM-000008 C58C1 Agrobacterium Chemically Competent Cells Transformation Protocol TD-P Revision 6.3 TD-P Date: 2/16/2023

Calculations

Transformation efficiency (TE) is defined as the number of colony forming units (cfu) produced by transforming 1 μ g of plasmid into a given volume of competent cells.

 $TE = Colonies/\mu g/Dilution$

Where:

Colonies = the number of colonies counted μg = amount of DNA transformed in μg Dilution = total dilution of the DNA before plating

Example:

Transform 5 μ l of (10 ng/μ l) pCAMBIA1391z control plasmid into 25 μ l of cells, add 975 μ l of Recovery Medium. Recover for 3 hours and plate 100 μ l. Count the colonies on the plate in two days. If you count 500 colonies, the TE is calculated as follows:

Colonies = 500 μg of DNA = 0.05 Dilution = 100/1000 = 0.1

 $TE = 500/0.05/0.1 = 1 \times 10^{5}$

Related Products

- AGL-1 Agrobacterium Chemically Competent Cells (GoldBio Catalog # CC-106)
- GV3101 Agrobacterium Chemically Competent Cells (GoldBio Catalog # CC-105)
- LBA4404 Agrobacterium Chemically Competent Cells (GoldBio Catalog # CC-107)
- EHA105 Agrobacterium Chemically Competent Cells (GoldBio Catalog # CC-108)
- C58C1 Agrobacterium Chemically Competent Cells (GoldBio Catalog # CC-109)
- Kanamycin (GoldBio Catalog # K-120)
- Rifampicin (GoldBio Catalog # R-120)

Web: www.goldbio.com
Email: contactgoldbio86@goldbio.com